






# Connecting to Canes Wi-Fi

## iOS (Apple) Mobile Devices

	
<p><b>STEP 1:</b> Select “Canes” from your list of available wireless networks.</p>	<p><b>STEP 2:</b> Enter in your CanesNet credentials.          Username: CanesNet Username          Password: CanesNet Password          Select “Join” in the upper-right corner.</p>
	
<p><b>STEP 3:</b> In the Certificate screen, select “Trust” in the upper-right corner.</p>	<p><b>END:</b> You are now connected to the new Canes wireless network!</p>





**\*\*\*If your device has been connected and you’ve changed your password, you will have to forget the network and re-enter your updated CanesNet credentials to re-connect.**

To forget the network:

- 1) Go to Settings > Wi-Fi
- 2) Tap the  next to “Canes”
- 3) Tap Forget This Network, then tap Forget to confirm.

# Connecting to Canes Wi-Fi

## Android & Chromebook Devices

	
<p><b>STEP 1:</b> Select “Canes” from your list of available wireless networks.</p>	<p><b>STEP 2:</b> Phase 1 should be set to ‘PEAP’ and Phase 2 is set to ‘MSCHAPV2’.</p>
	
<p><b>STEP 3:</b> Under Server CA Certificate select “Do not validate” or “Do Not Check”.</p> <p><i>*Some Chromebooks require you to choose Default</i></p>	<p><b>STEP 4:</b> Under Identity, enter in your CanesNet credentials. <b>Leave “Anonymous Identity” blank</b></p> <p>Identity: CanesNet Username          Password: CanesNet Password</p>
<p><b>STEP 5:</b> Click Connect.</p> <p><i>*If your Chromebook doesn’t connect, try restarting it before requesting help. Sometimes this really works!</i></p>	<p><b>END:</b> You are now connected to the new Canes wireless network!</p>

**\*\*\*If your device has been connected and you’ve changed your password, you will have to forget the network and re-enter your updated CanesNet credentials to re-connect.**





To forget the Network:

- 1) Go to Settings > Wi-Fi
- 2) For Androids, tap and hold on Canes; For Chromebooks, right-click on the “Canes” Network
- 3) Tap Forget network or Forget in the pop-up

# Connecting to Canes Wi-Fi

## Windows Devices

**\*GSW does not support connecting Windows 7 or Windows 8 laptops to our networks.**

	
<p><b>STEP 1:</b> Select 'Canes' from your list of available wireless networks.</p>	<p><b>STEP 2:</b> Enter your CanesNet credentials and click 'OK'.          User name: CanesNet Username          Password: CanesNet Password</p>
	
<p><b>STEP 3:</b> You will see a message that you are connecting to a new network "Canes" for the first time. Click 'Connect'.</p>	<p><b>END:</b> You are now connected to the new Canes wireless network.</p>


**\*\*\*If your device has been connected and you've changed your password, you will have to forget the network and re-enter your updated CanesNet credentials to re-connect.**

To forget the Network:


- 1) Click or tap the Wi-Fi icon in the bottom-right corner of the taskbar
- 2) Right-Click on the "Canes" Network and click "Forget"

# Connecting to Canes Wi-Fi


## Apple Computers/MacBooks




**STEP 1:** Select “Canes” from your list of available wireless networks.



**STEP 2:** Enter in your CanesNet credentials.  
 Username: CanesNet Username  
 Password: CanesNet Password



**STEP 3:** In the Verify Certificate screen, select “Continue” in the lower-right corner.



**END:** Enter your computer’s password to accept Certificate Settings. You are now connected to the new Canes wireless network!

**\*\*\*If your device has been connected and you’ve changed your password, you will have to you will have to forget the network and re-enter your updated CanesNet credentials to re-connect.**

To forget the Network:

- 1) Go to System Preferences, then click Network. Select Wi-Fi in the list on the left
- 2) Click the Advanced button, and Select “Canes”.
- 3) Click the remove button (–) beneath the list. You should no longer see Canes listed